



Wireless (WiFi) Denoto Configuration

Setting up a WiFi network is a relatively painless task. The following table lists the parts that are required to setup a wireless network.



Part	Description	Price
Wireless Router	<p>A wireless router acts as an information conduit. It receives information (packets) from one computer, and then it delivers to another computer on the (wireless) network. Each packet of information has the sender's address (commonly known as the IP address) and the recipient's IP address.</p> <p>Denoto transmits packets of testimony to the router and the router delivers those packets to the workstations.</p> <div style="text-align: right;">  </div> <p>A Wireless router is required to setup a WiFi network for your Denoto. Visit www.linksys.com for additional information on wireless routers.</p> <p>For maximum security, the encryption feature must be enabled. For your convenience, ProCAT offers pre-programmed routers.</p>	\$195.00
Wireless Adapter	<p>Most personal computers are equipped with a wireless adapter. You may use a built-in wireless adapter, or use an external device. These devices are common place. Visit www.linksys.com for additional information on wireless network adapters.</p>	95

	For your convenience, ProCAT offers the LinkSys USB adapters. Network configuration services are offered when the router and adapters are purchased from ProCAT.		
CAT 5 Cable	A standard twisted-pair cable is required to configure your wireless router.		9.5

Wi-Fi Configuration

Step	Instructions
1	Use a CAT-5 cable to connect a PC to the wireless router.
2	Use Internet Explorer to view the router's administration screen.
3	Assign 192.168.0.1 to the router.
4	Enable the WAP feature.
5	Record WAP password.
Realtime (Winner) Setup.	
1	Turn on the power to the court reporter's computer and search for the wireless network.
2	Click the Connect button, and then enter the WAP password to connect the realtime computer to the network.
3	Change the TCP/IP settings in the realtime computer to have a static IP address. Assign 192.168.0.2 to the realtime computer.
4	Disable the DHCP feature in the realtime computer.
5	Reboot the realtime computer.
6	Launch IPCONFIG after the computer boots up to verify the IP address assigned to the realtime computer.
7	Launch Winner Realtime Transcription.
8	Open the Preferences tab.
9	Select the Internet tab.
10	Enter 192.168.0.2 into the IP address field.
11	Click the OK button to store the settings.
Workstation (Denoto) Setup.	
1	Turn on the power to your attorney workstation.
2	Search for the wireless network.
3	Click the Connect button to establish a wireless connection to the router.
4	Enter the WAP password.
5	Launch the Wireless Network adapter properties to ensure automatic DHCP.
6	Launch Denoto software.
7	Open the Preference window.
8	Enter 192.168.0.2 into the Server IP address. This field indicates the input source – the address of the Winner Realtime computer.
9	Click the Save button to store the settings.